

All the information contained within the documentation is the property of MAZeT. Nothing from the catalogue may be reproduced or duplicated, neither electronically nor mechanically, unless with the express permission of MAZeT GmbH. All company and brand names as well as product descriptions referred to are generally subject to the protection of brand, patent, or goods laws.	VERSION AMENDMENTS		
	NO.	VERSION	APPROVED
	1	V 1.4	2006-07-10

Software Description

MTCS-C2-DLL MTCS-ME1-DLL

Library Description (MTCSApi.dll) API programming interface DLL

Revision 2.43

Table of Contents

1 Introduction	3
2 MTCS – FUNCTIONS	3
2.1 MTCS – Functions which are applicable to all MTCS-ME1 versions	3
2.1.1 <i>MTCSInitSystem</i>	3
2.1.2 <i>MTCSDllGetVersion</i>	4
2.1.3 <i>MTCSReadVersion</i>	4
2.1.4 <i>MTCSReadMemory</i>	4
2.1.5 <i>MTCSWriteMemory</i>	5
2.1.6 <i>MTCSSetUpdateMode</i>	5
2.2 MTCS – Functions which are applicable to the TOP, FRONT, DARK TIA versions	5
2.2.1 <i>MTCSGetADCxx</i>	5
2.2.2 <i>MTCSGetADCBL</i>	6
2.2.3 <i>MTCSGetADCAVR</i>	6
2.2.4 <i>MTCSGetADCBuf</i>	6
2.2.5 <i>MTCSGetADC</i>	7
2.2.6 <i>MTCSSetSwitch</i>	7
2.2.7 <i>MTCSSetEPoti</i>	7
2.3 MTCS – Functions which are applicable to DARK CCC versions	7
2.3.1 <i>MTCSSStartRGB, MTCSStopRGB, MTCSGetRGB</i>	7
2.3.2 <i>MTCSSStartRGB</i>	8
2.3.3 <i>MTCSStopRGB</i>	8
2.3.4 <i>MTCSGetRGB</i>	8

MAZeT GmbH Sales Department Göschwitzer Strasse 32 07745 Jena, Germany Tel.: +49 3641 2809-0 Fax: +49 3641 2809-12 Email: sales@MAZeT.de Website: http://www.MAZeT.de	Acknowledgement	Date	MAZeT GmbH	
	Created:	2006-07-10	Status: valid	
	Checked:	2006-07-10		
	Released:	2006-07-10	DOC. NO.: DB-05-171e	Page 1 of 15

Software Description MTCS-C2-DLL / MTCS-ME1-DLL (MTCSApi.dll)	VERSION		
	NO.	VERSION	APPROVED
	1	V 1.4	2006-07-10
2.4 MTCS – Functions which are applicable to the MTCS-C29 2.4.1 <i>MTCSGetADCAVR2</i>9 2.4.2 <i>MTCSGetADCSummen</i> 10 2.4.3 <i>MTCSSetParameter</i> 10 2.4.4 <i>MTCSSearchAmplification</i> 11 2.4.5 <i>MTCSWriteMemToAdr</i> 11 2.4.6 <i>MTCSReadMemFromAdr</i> 12 2.4.7 <i>MTCSGetSerienNummer</i> 13 3 BASIC FUNCTIONS FN.....13 3.1 <i>fnSendZeroPacket</i> 13 4 EEPROM.....13 5 TEST INTERFACE14			
All the information contained within this documentation relates to technology which is state-of-the-art at the time of publication and is of a provisional nature. MAZeT expressly reserves the right to make technical changes to equipment and components described in the documentation.		DOC. NO: DB-05-171E	Page 2 of 15

VERSION		
NO.	VERSION	APPROVED
1	V 1.4	2006-07-10

1 Introduction

The document describes the MTCSApi.dll as a gateway between the firmware on the Evaluation Kit MTCS-ME1 (Mod EVA) or the firmware on the board MTCS-C2 (Colorimeter2) and the user interface (host).

A USB 2.0 port is required for the software to be executable. The software was written for and tested with WindowsXP. Please pay attention to the firmware version for Mod EVA (>V2.22) and / or for Colorimeter2 (V0.13) and the version numbers of the DLL (> V2.43). The commands for Colorimeter2 only function with DLL Version 2.40 or later.

You can find the latest information and upgrade software in the download area at www.mazet.de. Please refer to data sheet MTCS-ME1 and / or MTCS-C2 for a better understanding of the hardware functionality.

The basic principle is that the host sends a request as a command to the Mod EVA. After processing the command, the Mod EVA sends its response to the host. The initiative always comes from the host and a response, which is forwarded after the command is sent, is always anticipated.

The MTCSApi.dll uses the USB port or the serial RS232 port (provided that this is available). In the delivery status, the value 0xff appears on address 0x3fe in the EEPROM and the board is activated via USB. If this address is allocated a 0, then the serial port is used in mode 57600,8,n,1 (provided that this is available).

The dll is located in the directory of the executable program. The lib necessary for program development is in the directory of the corresponding project.

```
#define USB_DLL_API __declspec(dllexport) __stdcall
```

2 MTCS – FUNCTIONS

2.1 MTCS – Functions which are applicable to all MTCS-ME1 versions

2.1.1 MTCSInitSystem

```
int USB_DLL_API MTCSInitSystem(char cTyp, int iVendorID, int iProductID);
```

Initialising the system

char cTyp	Type of connection between the board and the user interface
cTyp = 0	USB
	0xff must appear in address 0x3fe in the EEPROM
cTyp = 1	Serial port
	0 must appear in address 0x3fe in the EEPROM
int iVendorID	= 0x400 for Mod EVA
int iProductID	= 0xc35d
int iVendorID	= 0x152a for Colorimeter2
int iProductID	= 0x8220
Return value	= 0 No errors exist
	= -1 Internal initialisation error, reset Mod EVA
	= -2 Faulty device notification
	= -4 This Mod EVA has already been configured
	= -5 Device not found

VERSION		
NO.	VERSION	APPROVED
1	V 1.4	2006-07-10

2.1.5 MTCSWriteMemory

int USB_DLL_API MTCSWriteMemory(unsigned char cBuf, int iAnz);*

iAnz integrity values for the contents of the EEPROM are always written in bytes successively from address 0.

unsigned char* cBuf	Pointer on the buffer, which contains the contents for the EEPROM, (Param2 in the example)
int iAnz	The number of integrity values which are to be written. (Param1 in the example)
Return value	<div> <div>= 0</div> <div>No errors exist</div> </div> <div> <div>= 2</div> <div>Firmware detected an illegal command</div> </div> <div> <div>= 4..x</div> <div>Parameter error Parameter 1, or .. Parameter x</div> </div> <div> <div>= 6</div> <div>The number of integrity values exceeds the total number for EEPROM.</div> </div> <div> <div>= 7</div> <div>Transmission error</div> </div>

2.1.6 MTCSSetUpdateMode

int USB_DLL_API MTCSSetUpdateMode(void);

Shifts the firmware into update mode. After PowerUp Reset, the firmware can be updated using the "flip software" via the USB port. PowerUp Reset resets the Setup mode.

Return value	<div> <div>= 2</div> <div>Firmware detected an illegal command</div> </div> <div> <div>= 4..x</div> <div>Parameter error Parameter 1, or .. Parameter x</div> </div>
--------------	--

Other values are not possible as the USB port is no longer in use.

2.2 MTCS – Functions which are applicable to the TOP, FRONT, DARK TIA versions

2.2.1 MTCSGetADCxx

These commands are used for measuring reflective samples or sources with a constant brightness.

The brightness of the LED lighting (only with MTCS-ME1 FRONT and TOP) must be adjusted using MTCSSetEPoti.

“iCounts“ determines the number of measurement values, which are used to take an average.

VERSION		
NO.	VERSION	APPROVED
1	V 1.4	2006-07-10

2.2.5 MTCSGetADC

*int USB_DLL_API MTCSGetADC(unsigned short * usBuf);*

The ADC values UTD (AD value of the voltage of the isolating diode), URT (AD value Red), UGR (AD value Green), UBL (AD value Blue) are directly read out.

*unsigned short * usBuf* Pointer on the buffer, which contains the ADC values

Buffer size for the response from Mod EVA : 8 bytes

Return value

= 0	No errors exist
= 2	Firmware detected an illegal command
= 4..x	Parameter error Parameter 1, or .. Parameter x
= 7	Transmission error

2.2.6 MTCSSetSwitch

int USB_DLL_API MTCSSetSwitch(int iCounts);

The switch for transimpedance amplification of the isolating diode is set.

int iCounts Value, at which the switch is to be set
(Param1 in the example)

Return value

= 0	No errors exist
= 2	Firmware detected an illegal command
= 4..x	Parameter error Parameter 1, or .. Parameter x
= 7	Transmission error

2.2.7 MTCSSetEPoti

int USB_DLL_API MTCSSetEPoti(int iCounts);

The brightness of the LED lighting (only with MTCS-ME1 FRONT and TOP) is adjusted. The E-Poti is adjusted to the assigned value (0x00...0xFF).

int iCounts Value, at which the Epoti is to be set
(Param1 in the example)

Return value

= 0	No errors exist
= 2	Firmware detected an illegal command
= 4..x	Parameter error Parameter 1, or .. Parameter x
= 7	Transmission error

2.3 MTCS – Functions which are applicable to DARK CCC versions

2.3.1 MTCSStartRGB, MTCSStopRGB, MTCSGetRGB

These commands are used for measuring light sources e.g. with illumination LEDs and monitors.

The iTime parameter is entered into the integration time. It is variable between 5000µs and 25000µs.

It corresponds to the synchronisation of source frequencies (e.g. CRT monitors) 200Hz to 40Hz.

A measurement is carried out within a multiple of the given integration time. The measurement value ("ADC / number of iterations") represents the integral deviation of the signal lever divided by the number of integration intervals ("number of iterations").

With the "iZyklen" parameter, the stop criterion, the maximum number of recorded integration intervals, is defined for a measurement cycle.

VERSION		
NO.	VERSION	APPROVED
1	V 1.4	2006-07-10

2.3.2 MTCSStartRGB

int USB_DLL_API MTCSStartRGB(unsigned short usBuf, int iTime, int iZyklen);*

The interval time and the maximum number of integration cycles is defined.

RGB integration is started.

unsigned short* usBuf Pointer on the buffer, which contains the outcome message
 Buffer size for the response from Mod EVA : 2 bytes

int iTime Interval time
 (Param1 in the example)

int iZyklen max. integration cycles
 (Param2 in the example)

Return value = 0 No errors exist
 = 2 Firmware detected an illegal command
 = 4..x Parameter error Parameter 1, or .. Parameter x
 = 7 Transmission error

2.3.3 MTCSStopRGB

int USB_DLL_API MTCSStopRGB(unsigned short usBuf);*

The command stops a measurement and reads out the current RGB values and the number of intervals, which have occurred. The MTCSStopRGB command is not required during normal operation because the measurement is terminated after the number of iterations.

unsigned short* usBuf Pointer on the buffer, which contains the outcome message (red, green, blue and number of cycles for red, number of cycles for green, number of cycles for blue.
 Buffer size for the response from Mod EVA : 12 bytes

Return value = 0 No errors exist
 = 2 Firmware detected an illegal command
 = 4..x Parameter error Parameter 1, or .. Parameter x
 = 7 Transmission error

2.3.4 MTCSGetRGB

int USB_DLL_API MTCSGetRGB(unsigned short usBuf);*

The command reads out the current RGB values and the number of iterations, which have occurred.

unsigned short* usBuf Pointer on the buffer, which contains the outcome message (red, green, blue and number of iterations for red, number of iterations for green, number of iterations for blue.
 Buffer size for the response from Mod EVA : 12 bytes

Return value = 0 No errors exist
 = 2 Firmware detected an illegal command
 = 4..x Parameter error Parameter 1, or .. Parameter x
 = 7 Transmission error

VERSION		
NO.	VERSION	APPROVED
1	V 1.4	2006-07-10

2.4 MTCS – Functions which are applicable to the MTCS-C2

2.4.1 MTCSGetADCAVR2

int USB_DLL_API MTCSGetADCAVR2(int iIndex, unsigned short usBuf, int iCounts);*

The amplification and ADC mean values URT (AD value Red), UGR (AD value Green), UBL (AD value Blue) are directly read out using iCounts measurements.

The amplification can be set using MTCSsetParameter or determined automatically using MTCSsearchAmplification.

If the amplification factor is 0, the optimum amplification factor for the series of measurements is sought first. In addition, AD conversions on the red, green and blue channels are carried out until all channels provide values within a defined ADC operating range.

If the amplification factor is in the range (1, 8), the “automatic search of the optimum amplification factors” stage does not occur.

N series of measurements are carried out and the average value is generated.

If the subsequent measurement values differ from the first measurement value by more than 10%, then these are logged as error code 0xE003. (This serves as a reference to major sources of interference or pulsed light sources for which the measurement procedure is not suitable.)

These 3 mean values and the adjusted amplification factor are sent in the response to the host.

int iIndex	= 0	reserved for device number
int iCounts	The number of measurement values for averaging (Param1 in the example)	
unsigned short* usBuf	Pointer on the buffer, which contains the amplification factor and the ADC values Buffer size for the response from Col2 : 8 bytes	
Return value	= 0	No errors exist
	= 2	Firmware detected an illegal command
	= 3	Difference in measurement values is too large
	= 4..x	Parameter error Parameter 1, or .. Parameter x
	= 7	Transmission error

VERSION		
NO.	VERSION	APPROVED
1	V 1.4	2006-07-10

2.4.2 MTCSGetADCSummen

int USB_DLL_API MTCSGetADCSummen(int iIndex, unsigned long ulBuf, int iCounts);*

The amplification and ADC mean values URT (AD value Red), UGR (AD value Green), UBL (AD value Blue) are added together and read out using iCounts milliseconds.

The amplification can be set using MTCSsetParameter or defined automatically using MTCSsearchAmplification.

If the amplification factor is 0, the optimum amplification factor for the series of measurements is sought first. In addition, AD conversions on the red, green and blue channels are carried out until all channels provide values within a defined ADC operating range.

If the amplification factor is in the range (1, 8), the “automatic search of the optimum amplification factors” stage does not occur.

N series of measurements are carried out using iCounts milliseconds and the values are added together.

The adjusted amplification factor, the sum of the 3 AD values and the total number of measurements are sent in the response to the host.

All values are unsigned long values.

int iIndex	= 0	reserved for device number
int iCount		The number of milliseconds which are to be measured for the totals formation.
		(Param1 in the example)
unsigned long * ulBuf		Pointer on the buffer, which contains the amplification factor and the ADC values and the total number of measurements
		Buffer size for the response from Col2 : 20 bytes
Return value	= 0	No errors exist
	= 2	Firmware detected an illegal command
	= 3	Difference in measurement values is too large
	= 4..x	Parameter error Parameter 1, or .. Parameter x
	= 7	Transmission error

2.4.3 MTCSsetParameter

int USB_DLL_API MTCSsetParameter(int iIndex, int iCounts);

The amplification factor and tolerance parameters are set.

The default values are: Amplification factor = 8 Tolerance = 90(percent)

Both parameters are included in the “automatic search of the optimum amplification factors” stage.

int iIndex	= 0	reserved for device number
int iCounts		Amplification factor, 1 byte (low byte)
		Tolerance, 1 byte (high byte)
		(Param1 in the example)
Return value	= 0	No errors exist
	= 2	Firmware detected an illegal command
	= 7	Transmission error

VERSION		
NO.	VERSION	APPROVED
1	V 1.4	2006-07-10

2.4.4 MTCSSearchAmplification

int USB_DLL_API MTCSSearchAmplification(int iIndex, unsigned short usBuf, int iLimit);*

Search for the optimum amplification factor

The optimum amplification factor for the series of measurements is sought. In addition, AD conversions on the red, green and blue channels are carried out with a decreasing amplification factor until the strongest channel provides a signal which is below the limit value (value range 1..100%).

The measurement values are expanded according to the bit shifting parameter.

The located amplification factor and the last 3 measurement values from the algorithm are sent in the response to the host.

The located amplification factor is set for the following measurements.

Note

This algorithm can also be used to bring the AD conversions into an optimum operating range. This is essential if, due to very bright light sources, the colour sensor is overloaded when the amplification factor is at its highest. Therefore, the AD conversion would always provide the maximum AD values.

int iIndex	= 0	reserved for device number
int iLimit		Limit values (in %), 1 byte
unsigned short * usBuf		Pointer on the buffer, which contains the amplification factor and the ADC values
		Buffer size for the response: 8 bytes
Return value	= 0	No errors exist
	= 2	Firmware detected an illegal command
	= 7	Transmission error

2.4.5 MTCSWriteMemToAdr

int USB_DLL_API MTCSWriteMemToAdr(int iIndex, unsigned char cBuf, int iAdr, int iAnz)*

iAnz integrity values for the contents of the EEPROM are always written in bytes successively from address iAdr.

iAnz items are written as a data stream in the external EEPROM from a defined address iAdr.

iAnz = (1, 57)

The size of the EEPROM is 128 bytes. It can also be addressed in the range (0x00, 0x6F). If address + 2*number data items to be written is larger than the above address, error code 6 is restored.

VERSION		
NO.	VERSION	APPROVED
1	V 1.4	2006-07-10

2.4.7 MTCSGetSerienNummer

void USB_DLL_API MTCSGetSerienNummer (int ilIndex, char cBuf);*

Read the serial numbers from the board's EEPROM

int ilIndex = 0 reserved for device number
char* cBuf Pointer on the buffer, which contains the serial numbers
which are in the USB descriptor.
Buffer size for the response from Colorimeter2 : 16 bytes
Return value = 0 No errors exist
 = 2 Firmware detected an illegal command
 = 7 Transmission error

3 BASIC FUNCTIONS FN...

3.1 fnSendZeroPacket

void USB_DLL_API fnSendZeroPacket(void);

Sends synchronisation string

4 EEPROM

The contents of the EEPROM is structured.

System parameters are data which are saved permanently.

Access to the data is gained using the ReadMemory, WriteMemory, WriteMemToAdr and ReadMemFromAdr commands. These commands treat the memory as a data stream.

The maximum size of the EEPROM of the Mod EVA is 1024 bytes. The last 10 bytes are reserved for internal characteristics. Only essential data should be written to the EEPROM because writing to the EEPROM is a slow process.

No.	Contents	Length in WORD
1.	Application code	1
2.	E-Poti	1
3.	Dark value	3
4.	White value	3
5.	BL (stray light compensation 0=off, 1=on)	1
6.	Number of average value	1
7.	Integration time	1
8.	Correction matrix sensor	9
9.	Correction matrix display	9
10.	Free memory	

Table 1: Overview relating to the system parameters in the EEPROM of the Mod EVA

The maximum size of the EEPROM of the Colorimeter 2 is 128 bytes.

The top 16 bytes are reserved for the serial numbers.


Software Description MTCS-C2-DLL / MTCS-ME1-DLL (MTCSApi.dll)		VERSION		
		NO.	VERSION	APPROVED
		1	V 1.4	2006-07-10

No	Contents	Length in WORD	Comments
1	Application code	1	The application code for the Colorimeter 2 is 0x0011
2	E-Poti	1	No relevance
3	Dark value	3	Is the parameter for the PC application
4	White value	3	Is the parameter for the PC application
5	Stray light compensation BL	1	No relevance
6	Number of average values	1	For GetADCAvr2
7	Amplification factor	1	For GetADC2, GetADCAvr2
8	Correction matrix sensor	9	is the parameter for the PC application
9	Correction matrix display	9	is the parameter for the PC application
10			

Table 2: Overview relating to the system parameters in the EEPROM of the Colorimeter2

5 TEST INTERFACE

The project “ddl_test.dsw” is a c++ project for Microsoft Visual Studio 6.0 and indicates the use of the individual functions used in the dll.



Software Description

MTCS-C2-DLL / MTCS-ME1-DLL (MTCSApi.dll)

VERSION		
NO.	VERSION	APPROVED
1	V 1.4	2006-07-10

The system is initialised during startup using MTCSInitSystem().

It is possible to access MTCS... with a maximum of 2 entry parameters. The meaning of the parameters is to be inferred from the command description. Loop contains the number of cycles for the command which has been accessed. This loop can be cancelled using "Abort Loop".

"Clear Window" clears the current display window. All entered parameters are interpreted as decimal numbers, VendorID and ProductID are interpreted as hexadecimal numbers.

For further information please contact:

MAZeT GmbH

Sales Department:

Göschwitzer Strasse 32

07745 Jena, Germany

Tel: +49 3641 2809-0

Fax: +49 3641 2809-12

Email: sales@MAZeT.de

Website: <http://www.MAZeT.de>